

Basic Configuration Commands

Command	Purpose
enable	Logs you into enable mode, which is also known as user exec mode or privileged mode
configure terminal	Logs you into configuration mode
interface <i>fastethernet/number</i>	Enters interface configuration mode for the specified fast ethernet interface
reload	An exec mode command that reboots a Cisco switch or router
hostname <i>name</i>	Sets a host name to the current Cisco network device
copy <i>from-location to-location</i>	An enable mode command that copies files from one file location to another
copy running-config startup-config	An enable mode command that saves the active config, replacing the startup config when a Cisco network device initializes
copy startup-config running-config	An enable mode command that merges the startup config with the currently active config in RAM
write erase erase startup-config	An enable mode command that deletes the startup config
ip address <i>ip-address mask</i>	Assigns an IP address and a subnet mask
shutdown no shutdown	Used in interface configuration mode. "Shutdown" shuts down the interface, while "no shutdown" brings up the interface.
ip default-gateway <i>ip_address</i>	Sets the default gateway on a Cisco device
show running-config	An enable mode command that displays the current configuration
description <i>name-string</i>	A config interface command to describe or name an interface
show running-config interface <i>interface slot/number</i>	An enable mode command to display the running configuration for a specific interface

<code>show ip interface [type number]</code>	Displays the usability status of interfaces that are configured for IP
<code>ip name-server serverip-1 serverip-2</code>	A configure mode command that sets the IP addresses of DNS servers

Troubleshooting Commands

<code>ping {hostname system-address} [source source-address]</code>	Used in enable mode to diagnose basic network connectivity
<code>speed {10 100 1000 auto}</code>	An interface mode command that manually sets the speed to the specified value or negotiates it automatically
<code>duplex {auto full half}</code>	An interface mode command that manually sets duplex to half, full or auto
<code>cdp run</code> <code>no cdp run</code>	A configuration mode command that enables or disables Cisco Discovery Protocol (CDP) for the device
<code>show mac address-table</code>	Displays the MAC address table
<code>show cdp</code>	Shows whether CDP is enabled globally
<code>show cdp neighbors [detail]</code>	Lists summary information about each neighbor connected to this device; the “detail” option lists detailed information about each neighbor
<code>show interfaces</code>	Displays detailed information about interface status, settings and counters
<code>show interface status</code>	Displays the interface line status
<code>show interfaces switchport</code>	Displays a large variety of configuration settings and current operational status, including VLAN trunking details.
<code>show interfaces trunk</code>	Lists information about the currently operational trunks and the VLANs supported by those trunks
<code>show vlan</code> <code>show vlan brief</code>	Lists each VLAN and all interfaces assigned to that VLAN but does not include trunks

Routing and VLAN Commands

ip route <i>network-number network-mask</i> <i>{ip-address interface}</i>	Sets a static route in the IP routing table
router rip	Enables a Routing Information Protocol (RIP) routing process, which places you in router configuration mode
network <i>ip-address</i>	In router configuration mode, associates a network with a RIP routing process
version 2	In router configuration mode, configures the software to receive and send only RIP version 2 packets
no auto-summary	In router configuration mode, disables automatic summarization
default-information originate	In router configuration mode, generates a default route into RIP
passive-interface <i>interface</i>	In router configuration mode, sets only that interface to passive RIP mode. In passive RIP mode, RIP routing updates are accepted by, but not sent out of, the specified interface.
show ip rip database	Displays the contents of the RIP routing database
ip nat [<i>inside outside</i>]	An interface configuration mode command to designate that traffic originating from or destined for the interface is subject to NAT
ip nat inside source <i>{list{access-list-number access-list-name}}</i> <i>interface type number[overload]</i>	A configuration mode command to establish dynamic source translation. Use of the “list” keyword enables you to use an ACL to identify the traffic that will be subject to NAT. The “overload” option enables the router to use one global address for many local addresses.
ip nat inside source static <i>local-ip global-ip</i>	A configuration mode command to establish a static translation between an inside local address and an inside global address

vlan	Creates a VLAN and enters VLAN configuration mode for further definitions
switchport access vlan	Sets the VLAN that the interface belongs to.
switchport trunk encapsulation dot1q	Specifies 802.1Q encapsulation on the trunk link.
switchport access	Assigns this port to a VLAN
vlan vlan-id [<i>name vlan-name</i>]	Configures a specific VLAN name (1 to 32 characters)
switchport mode { <i>access</i> <i>trunk</i> }	Configures the VLAN membership mode of a port. The access port is set to access unconditionally and operates as a non-trunking, single VLAN interface that sends and receives non-encapsulated (non-tagged) frames. An access port can be assigned to only one VLAN. The trunk port sends and receives encapsulated (tagged) frames that identify the VLAN of origination. A trunk is a point-to-point link between two switches or between a switch and a router.
switchport trunk { <i>encapsulation</i> { <i>dot1q</i> }	Sets the trunk characteristics when the interface is in trunking mode. In this mode, the switch supports simultaneous tagged and untagged traffic on a port.
encapsulation dot1q vlan-id	A configuration mode command that defines the matching criteria to map 802.1Q frames ingress on an interface to the appropriate service instance

DHCP Commands

ip address dhcp	A configuration mode command to acquire an IP address on an interface via DHCP
ip dhcp pool name	A configuration mode command to configure a DHCP address pool on a DHCP server and enter DHCP pool configuration mode
domain-name <i>domain</i>	Used in DHCP pool configuration mode to specify the domain name for a DHCP client
network <i>network-number [mask]</i>	Used in DHCP pool configuration mode to configure the network number and mask for a DHCP address pool primary or secondary subnet on a Cisco IOS DHCP server
ip dhcp excluded-address <i>ip-address [last-ip-address]</i>	A configuration mode command to specify IP addresses that a DHCP server should not assign to DHCP clients
ip helper-address <i>address</i>	An interface configuration mode command to enable forwarding of UDP broadcasts, including BOOTP, received on an interface
default-router <i>address[address2 ... address8]</i>	Used in DHCP pool configuration mode to specify the default router list for a DHCP client

Security Commands

password <i>pass-value</i>	Lists the password that is required if the login command (with no other parameters) is configured
username <i>name password pass-value</i>	A global command that defines one of possibly multiple user names and associated passwords used for user authentication. It is used when the login local line configuration command has been used.
enable password <i>pass-value</i>	A configuration mode command that defines the password required when using the enable command
enable secret <i>pass-value</i>	A configuration mode command that sets this Cisco device password that is required for any user to enter enable mode
service password-encryption	A configuration mode command that directs the Cisco IOS software to encrypt the passwords, CHAP secrets, and similar data saved in its configuration file
ip domain-name <i>name</i>	Configures a DNS domain name
crypto key generate rsa	A configuration mode command that creates and stores (in a hidden location in flash memory) the keys that are required by SSH
transport input { <i>telnet ssh</i> }	Used in vty line configuration mode, defines whether Telnet or SSH access is allowed into this switch. Both values can be specified in a single command to allow both Telnet and SSH access (default settings).
access-list <i>access-list-number {deny permit} source [source-wildcard] [log]</i>	A configuration mode command that defines a standard IP access list
access-class	Restricts incoming and outgoing connections between a particular vty (into a basic Cisco device) and the addresses in an access list
ip access-list { <i>standard extended</i> } { <i>access-list-name access-list-number</i> }	A configuration mode command that defines an IP access list by name or number

permit source [<i>source-wildcard</i>]	Used in ACL configuration mode to set conditions to allow a packet to pass a named IP ACL. To remove a permit condition from an ACL, use the “no” form of this command.
deny source [<i>source-wildcard</i>]	Used in ACL configuration mode to set conditions in a named IP ACL that will deny packets. To remove a deny condition from an ACL, use the “no” form of this command.
ntp peer < <i>ip-address</i> >	Used in global configuration mode to configure the software clock to synchronize a peer or to be synchronized by a peer
switchport port-security	Used in interface configuration mode to enable port security on the interface
switchport port-security maximum maximum	Used in interface configuration mode to set the maximum number of secure MAC addresses on the port
switchport port-security mac-address { <i>mac-addr</i> { <i>sticky</i> [<i>mac-addr</i>]}}	Used in interface configuration mode to add a MAC address to the list of secure MAC addresses. The “sticky” option configures the MAC addresses as sticky on the interface.
switchport port-security violation { <i>shutdown</i> <i>restrict</i> <i>protect</i> }	Used in interface configuration mode to set the action to be taken when a security violation is detected
show port security [<i>interface interface-id</i>]	Displays information about security options configured on the interface
terminal monitor	An enable mode command that tells Cisco IOS to send a copy of all syslog messages, including debug messages, to the Telnet or SSH user who issues this command